

- **Print from your Chromebook (without Cloud Print)!**


Video - [Print from your Chromebook \(cloud print replacement\) - YouTube](#)

Webpage Link - [Print from a Chromebook without Cloud Print! \(2021 update\) \(chrbook.com\)](#)

- **CONNECT A PRINTER PHYSICALLY TO YOUR CHROMEBOOK**

If you're using a much older printer that isn't internet-capable, or if it is internet-capable but you're having trouble connecting it manually as described above, don't fret. You can connect your printer physically to a Chromebook using a USB cable.

- Plug the cable into your printer, and then plug the other end into your Chromebook.
- You should see a box in the lower right-hand corner of screen that says your printer is installed.



- Please note that it take a few min for the printer to show in the Chrome browser after it is installed.
- **If your printer does not install automatically try the steps below.**
 - Open your Chromebook's settings and type "print" into the search box.
 - Select "Printers," and then click the blue "Add Printer" button.
 - Click on your printer's name and click the blue "Add" button to finish.

That's it! Now just hit Ctrl-P from any browser tab or look for the "Print" command in any app and prepare to print to your heart's content.


• ADD A “Newer” WIRELESS PRINTER

Provided you have a reasonably recent printer that’s capable of connecting to the internet, you should be able to add it directly to your Chromebook without the need for supplementary services.

First, make sure the printer is on and connected to the same Wi-Fi network as your computer. The procedure for connecting a printer to Wi-Fi varies from one model to the next, but there’s generally a “Wi-Fi” or “internet” option somewhere on the printer’s display, either as an icon on the main screen or as an option in its settings menu. This should walk you through the process.

Got the printer online and ready? Here’s what to do next:

- Click the clock in the lower-right corner of your Chromebook’s screen. Then click the gearshaped icon to open its settings.
- Type “print” into the search box at the top of the settings panel.
- Select “Printers,” then click the blue “Add Printer” button.
- Click on your printer’s name in the list that appears and click the blue “Add” button to finish the pairing.



• ADD AN “Older” WIRELESS PRINTER

If your printer doesn't appear in the list (which may happen if it's an older device), you'll need to click the “Add Manually” button that appears on the lower left corner of that window.

- Give the printer any name you want.
- Type its IP address into the “Address” box. (You can usually find the IP address somewhere in the printer's display menu. Try looking in its settings for a section about network or wireless configuration.)
- Leave the other two fields as they are and click the blue “Add” button. Type in your printer's manufacturer (e.g., “HP”) and model (e.g., “Officejet Pro 8600”), and select the appropriate options as they appear. Click the blue “Add” button when you're done. GRID VIEW

